

## Calibrating the 8" Touch Dynamic Touch Screen Computer

1. Download the utility from the Procare Knowledge Base:
  - a. <http://procaresupport.com/Resources/Knowledge-Base/Hardware/8--Touch-Dynamic-Calibration-Utility.aspx>
2. Extract the file and run the Setup file.
3. Go to Start > All Programs > Touch Utility
4. Run 'Touch Utility'
5. If you get an error that says "No Device was found", follow these steps:



- a.
- b. Go to Start > All Programs > Touch Utility
- c. Run 'Scan32 Touch Devices'
- d. Close this window when it is done. It should have found a device



- e.
- f. If it didn't find anything then reboot and try again.

6. You should be looking at the main screen of POS Touch



a.

7. Click on the 'Device' tab



a.

8. Click on the button that says '3 points'
9. Follow the instructions.
10. If this doesn't fix the calibration issue click on the 'Release Comport and Exit' button and then follow these instructions again starting at Step 3.